

Snappy Driver Installer Origin



Reference Manual

by Glenn Delahoy

© Copyright 2017

Last Updated: 4 October 2017

Snappy Driver Installer Origin

Reference Manual

Table of Contents

General Information.....	3
Introduction.....	4
Getting Set Up.....	5
Using Snappy Driver Installer Origin.....	7
Application and Driver Pack Updates.....	9
System Menu Options.....	11
Create A USB Drive Wizard.....	13
Command Line Reference.....	15
Deprecated Options.....	17
Verbose.....	18
Configuration File Reference.....	19
Keyboard Actions.....	22
Scripting.....	24
Running A Script.....	24
Config File.....	24
Script Commands.....	25
Translation Tool.....	30

General Information

GNU General Public License

This program is free software: you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation, either version 3 of the license or (at your option) any later version.

This program is distributed in the hope that it will be useful but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

Developers

BadPointer, Glenn Delahoy

Tools

Snappy Driver Installer Origin uses the following technologies:

- WebP is licensed under the terms of the BSD license.
- libTorrent is licensed under the terms of the BSD license.
- Backtrace is licensed under the terms of the BSD license.
- 7-Zip is licensed under the terms of the GNU Library or Lesser General Public License version 2.
- Driver Packs courtesy of SamLab.

Official Web Site

www.snappy-driver-installer.org

Patreon Home page

https://www.patreon.com/sdi_tool

Source Forge

<https://sourceforge.net/projects/snappy-driver-installer-origin/>

Translations

Send your updated language files to translations@snappy-driver-installer.org. Your updates will be included in the next release. This is not a support email so you won't get a reply.

Introduction

Welcome to Snappy Driver Installer Origin, the original free and clean driver updater for technicians. It's fast, portable and scriptable to help you get your job done faster. It can be used offline via a USB drive to install drivers where Internet isn't available. It can be run over a local network for corporate or workshop environments. No more searching for drivers after a clean install, just let Snappy Driver Installer Origin do it's thing and your job will be done in no time. The perfect technician's tool.

This document is a work in progress. If you see any errors or knowledge gaps please let me know so I can make it the most complete reference manual possible.

If you appreciate my hard work please support me at the Patreon page listed earlier or just a single donation via Paypal on the home page of the official web site, also listed earlier.

Getting Set Up

If you downloaded the entire package with a torrent client then you're ready to begin work immediately. There's nothing else to do. SDIO is portable and does not need to be installed into Windows. You just copy it to wherever you need it to work. That might be a USB thumb drive, the program files folder of the PC or anywhere else on a computer that's convenient.

If you downloaded the zip file from the home page, you should unzip it to a disk with at least 15GB of free space.

There are two executable files: SDIO_Rxxx.exe is the 32 bit version and SDIO_x64_Rxxx.exe is the 64 bit version. The "xxx" is the particular revision you downloaded. You'll obviously need to run the 32 bit version in a 32 bit Windows environment but you can run either version in a 64 bit Windows environment although the 64 bit version will give you better performance. There is a batch file called SDIO_auto.bat which automatically detects and runs the correct architecture.

When you run SDIO for the first time you'll be presented with the Welcome screen.




SDIO can work "offline" or "online". What this means is it can have the driver packs stored locally with the application or available for download as required.

If you choose to work "offline", that is, you want to have all the drivers available locally then you should download all the driver packs now. Be prepared to come back tomorrow; they are big and will take some time to download. When the download is complete and the driver packs are indexed, you're ready to start working offline.


If you choose to work "online", that is, you want to download driver packs only as required then you should download the indexes now. When this is complete, SDIO will know what driver packs are available for download and can begin matching your computer's devices. SDIO automatically indexes downloaded driver packs and keeps track of what's offline and what's online. When you scan a computer, SDIO will match all indexed drivers, both online and offline. If it finds a good match online, it will display a message to that effect ("Internet") so that you know the driver pack will need to be downloaded. During installation, any missing driver packs are automatically downloaded.

The third option on the Welcome screen is Download Network Drivers Only. This option is often used to get freshly installed computers online quickly by installing just the required network drivers. This will also download the online indexes.

There is another option which is to do nothing, click the Close button. SDIO is not very useful in this state as it has nothing to match your devices against. However it does report that driver packs are available to download.



When you click on that bar, a dialog will pop up where you can select which driver packs you want to download. If you know what you're looking for this is the best way to achieve it. Simply select the category you want and possibly the indexes as well and click the Ok button.



SDIO will begin downloading the selected driver packs. When it's done, everything is indexed, your computer's devices are rescanned and the results displayed.

If you're looking to get some other computer running you can either run the *Create USB Drive* wizard from the system menu or close SDIO and copy the entire folder to a thumb drive and run it on the other computer.

Using Snappy Driver Installer Origin

Having downloaded the driver packs and/or online indexes, you can now begin using the application.

SDIO will scan your computer and display a list of devices that match the given filters. The default filters are *Not installed*, *Newer* and *Better Match*. Any device that matches any of these will be displayed. If you want to change the filters it uses, select the *Expert Mode* check box. Additional options will be displayed including the filter options.



From here, you simply check the devices you want to update and click the *Install* button. SDIO will begin extracting the required device drivers from it's driver packs and install them.

If you have downloaded the online indexes and SDIO requires a device driver contained in a driver pack it doesn't yet have, it will download the pack before proceeding with the installation.

Here's a few recommendations:


- You should always check the *Create A Restore Point* option so you can roll back if necessary. Restore points are cheap, only take a few seconds to create and can be a life saver if things go south.
- Don't install too many drivers at once. Most of the time it will be fine but then you'll strike that one time you'll wreak havoc on the system that can only be undone by rolling back **all** the driver installations.
- If you need to install USB 3 drivers, you should install them all at once. Essentially, the 3 drivers, iusb3hub, iusb3xhc, iusb3hcs should always be installed together. The PCI bus

(iusb3hcs) must be the same version as iusb3hub and iusb3xhc. Make sure you are not running SDIO from a USB 3 port.

- Newer is not always better. If you want to be conservative, uncheck the *Newer* filter so you only install missing and better matched drivers.


Application and Driver Pack Updates

Snappy Driver Installer Origin automatically checks for updates each time you start the application. If it finds application or driver pack updates it will alert you via the Updates bar on the main window.



You should avoid downloading updates when running from a USB drive if it has limited space available. The updates require at least as much free space as the total download size.

To begin updating, click the bar to open the Update dialog.



Here you can select any of the available updates or use the Selection buttons at the bottom to make your selection:

- Check All : Select all available updates.
- Uncheck All : Clear the current selection.
- This PC only : Select updates appropriate for the current PC. If this is the first time using SDIO or you have not yet downloaded the indexes, this option cannot select appropriate

driver packs. What it will do instead is select the indexes. Once you have downloaded the online indexes and your computer's devices have been rescanned, you can return to the Update dialog to select driver packs for this PC.


- Network Only : This selects all the LAN, WWAN and Wifi driver packs. This is often used to get another computer online quickly by downloading and installing only the network drivers.

Other options are:


- Show only updates : This will hide updates for any driver packs that you don't already have. The result being you only update the driver packs you are interested in.
- Continue seeding : This keeps the update session active so you can join in sharing the updates with other users around the world. Your new downloads are not indexed until you stop sharing. If you intend to start the updates and leave it unattended, this option is a great way to give back to the community by sharing what you have.

System Menu Options

The System menu can be accessed either by clicking on the icon at the top left of the application main window as illustrated here:



or by right clicking anywhere on the application title bar as illustrated here:




- **Start seeding driver packs** : This will share whatever driver packs you have previously downloaded and exist in your working drivers directory. It will share using whichever update torrent is currently selected. It will perform a file verification check first to match your driver pack files against the torrent. If it thinks there's any pieces missing, it will download those first then switch to seeding mode and stay there until you switch it off.
- **Select SDIO Updates** : This selects the regular SDIO update torrent. This is the one we've always used which includes the application updates and the latest driver pack updates available at the time of the SDIO release. If you do nothing you will always use the SDIO updates, which is perfectly fine and will keep you up to date with the latest SDIO and to within a few weeks of being up to date with the latest driver packs.

- **Select Driver Packs Updates :** The second update torrent is the driver packs update torrent from SamLab. If you absolutely must have the very latest driver packs then you can select this torrent to see if there are any driver pack updates released since the last official SDIO release. Both updates end up in the same location, your working drivers directory, so you can freely switch between the two to ensure you have the latest of everything. You can choose to seed either torrent if you like; first select the desired updates torrent then select Start Seeding Driver Packs. It will share the contents of your working drivers directory to the selected torrent.
- **Tools :** This is a collection of useful Windows tools such as Device Manager, Control Panel, System Protection etc. Some tools don't work on Windows XP.
- **Open Logs :** This opens File Explorer to the logs directory.
- **Select Driver Directory :** This changes the current working drivers directory. This is useful if you have your own driver collection or have created a sub collection of drivers in a different location to your normal working drivers.
- **Create A USB Drive :** This wizard will guide you through the process of creating a portable copy of SDIO on a selected USB drive. See the *Create A USB Drive* chapter for details.
- **About :** Shows the application About box with copyright information, license information etc.
- **License Information :** Displays the entire GNU General Public License.

Create A USB Drive Wizard

This wizard makes it easy to create a portable thumb drive version of SDIO from your master copy. The files will be copied to the root directory of the selected device. You should ensure the device has sufficient capacity to store the required files. A full version including all driver packs is currently over 13GB, network driver packs only is under 1GB. The wizard will give you the option to clear files from the drive or do a Quick Format of the drive and will keep you up to date on the size of all selected files and the available space on the selected device.

Click the *Next* button to begin.



Target Drive

Insert your removable USB drive and wait for Windows to install it. It will then appear in the selection list with total capacity and available capacity in megabytes.


By default SDIO includes all available driver packs and this is reflected in the *Space Required* figure at the bottom of the wizard.

Click the *Delete Files* button to delete all files from the USB drive. Click the *Quick Format* button to initiate the Windows Quick Format

dialog. In Windows XP, this dialog defaults to a full format with the option to choose a quick format. On later versions of Windows this dialog defaults to quick format with the option to choose a full format. Click *Next* to continue.

Driver Packs

This page allows you to select the driver packs you want to include. The default is to include all active driver packs. If you have downloaded all driver packs this will be over 13GB. If you have not downloaded all driver packs, this will be less. You can choose to include just the network driver packs. This is quite small and is most often used to get a new Windows installation online quickly.




The third option will select all the driver packs that contain the drivers selected on the main window. If you had any drivers selected prior to opening the wizard, this option will be automatically selected. You can select the driver packs relevant to the current machine by choosing the *Current* option followed by the *Select all* option.

You can elect to include no driver packs if you want just the application without driver packs.

You can optionally specify an additional directory containing drivers or driver packs. This directory and its contents will be copied verbatim into the *drivers* directory of the target USB drive. This allows you to include custom driver packs, uncompressed/extracted driver packs or your own collection of drivers.

Finally, you can choose to include the online indexes if you have them. This allows you to run SDIO on any machine with an internet connection and download the required driver packs.



Environment

This page provides options for including languages and themes and for modifying the application configuration.

You can include all languages or just the language you are currently using.


You can include all themes, just the theme you are currently using or the default internal theme (Metallic).

You can preset a few SDIO configuration items and optionally include the *autorun.inf* and

SDIO_auto.bat files in the root directory of the drive.

Ready To Begin

When you're happy with your configuration, click the *Finish* button and the process of copying the selected files to your USB drive will begin. A progress dialog will appear to keep you apprised of the progress.



Command Line Reference

All commands begin with a dash, “-”. In addition to the following commands, any option or setting listed in the Configuration File chapter can be added to the command line.

-?

Show the help window.

-script:<scriptfile> [options ...]

Execute the given script with options. If this option is found on the command line, all options before it are ignored. See the Scripting chapter for details.

-cfg:<filename>

Loads the configuration from the given file. See the Configuration File chapter for details.

-7z

Executes the given 7-zip command. For details, see the 7-zip manual. An error of 2 usually means "File Not Found". Use this to extract driver packs manually.

```
SDIO.exe -7z x DP_TV_Beholder_14020.7z
```

-install <hwid> <infile>

-HWIDInstalled:<hwid>=<file>

-save-installed-id[:<file>]

-delextrainfs

Deletes unused inf files after extracting.

-verbose:<flags>

Sets log detail level.

-ls:<file>

Loads snapshot.

-nologfile

Suppress creating logs.

-nosnapshot

Suppress creating snapshots.

-nostamp

Creates logs and snapshot without timestamps.

-getdevicelist:<file>

Writes a text file containing details of all installed devices and drivers.

-activetorrent:<num>

Select the active update torrent. By default the active update torrent is 1 which is the SDIO application and driver pack updates. You can also select 2 which is the driver pack update torrent. The driver packs are updated more frequently than the SDIO application so if you absolutely must have the very latest driver packs, you can set the active update to 2 and download the very latest.

You can also do this from the System Menu on the main application window.

-a:32

Emulate a 32 bit Windows environment.

-a:64

Emulate a 64 bit Windows environment.

-v:<version>

Emulate any given Windows version.

-extractdir:<dir>

Use the given directory to extract the driver packs. The default is "%temp%\SDI".

-keeptempfiles

Do not delete extracted driver pack files.

-finish_cmd

Specifies a command executed upon completion of driver installation.

-finishrb_cmd

Specifies a command executed upon completion of driver installation when a reboot is required.

-finish_upd_cmd

Specifies a command executed upon completion of driver pack updates.

-keepunpackedindex

Prevents updating indexes for unpacked drivers.

-failsafe

Disables indexing WINDOWS\Inf.

-disableinstall

Disables driver installation and restore point creation.

-reindex

Force reindexing of all driver packs.

-index_hr

Creates text format (so called human readable) indexes.

-preservecfg

Do not overwrite the configuration file.

Deprecated Options

The following options are deprecated and will eventually be removed. You should start transitioning your scripts to the new scripting tool.

-PATH <pathtodrivers>

-nogui

Runs without GUI interface.

-autoupdate

Automatically downloads all available driver pack updates.

-autoclose

Automatically close the application after downloading driver pack updates. If -autoinstall is specified, the application will close after installation is complete.

-autoinstall

Automatically begin driver installation.

Verbose

The `-verbose:<flags>` switch is used to set log detail level. For example, in order to log only sections `DeviceInfo` and `manager_print` you have to calculate the sum: $4+16=20$.

```
SDIO.exe -verbose:20
```

LOG_VERBOSE_ARGS	0x0001	1	Sections: "Settings".
LOG_VERBOSE_SYSINFO	0x0002	2	Sections: "Windows", "Environment".
LOG_VERBOSE_DEVICES	0x0004	4	Sections: "DeviceInfo".
LOG_VERBOSE_MATCHER	0x0008	8	Sections: "{matcher_print".
LOG_VERBOSE_MANAGER	0x0010	16	Sections: "{manager_print".
LOG_VERBOSE_DRP	0x0020	32	Sections: "Driverpacks".
LOG_VERBOSE_TIMES	0x0040	64	Sections: "Times".
LOG_VERBOSE_LOG_ERR	0x0080	128	Error messages.
LOG_VERBOSE_LOG_CON	0x0100	256	Misc messages.
LOG_VERBOSE_LAGCOUNTER	0x0200	512	GUI lag counter.
LOG_VERBOSE_DEVSYNC	0x0400	1024	Sections: "{Updated".
LOG_VERBOSE_BATCH	0x0800	2048	Batch processing of snapshots.
LOG_VERBOSE_DEBUG	0x1000	4096	Debug output.
LOG_VERBOSE_TORRENT	0x2000	8192	Torrent output

Configuration File Reference

The configuration file is called “sdi.cfg” by default but you can call it anything or have many configuration files and use the “-cfg” command line option to load the required configuration file.

The following commands and settings may be added to the cfg file. If these commands or settings are included as a parameter on the command line, they will be saved to the cfg file.

If the -preservecfg command line option is used, the cfg file will not be updated.

-drp_dir:<dir>

Path to driver packs.

-index_dir:<dir>

Path to indexes.

-output_dir:<dir>

Path to indexes in human-readable format.

-data_dir:<dir>

Path to translations and themes.

-log_dir:<dir>

Path to logs and snapshots.

-lang:<name>

Current interface language.

-theme:<name>

Current theme.

-hintdelay:<time>

Sets hint delay.

-wndwx:<num>

Sets window width.

-wndwy:<num>

Sets window height.

-wndsc:<num>

Sets window show command (1=show normal, 2=minimized, 3=maximized).

-scale:<size>

Sets scaling for GUI (normal size: 256).

-filters:<flags>

Sets filters.

-port:<num>

-downlimit:<num>

-uplimit:<num>

-connections:<num>

-expertmode

Enable the expert mode.

-showconsole

-norestorepnt

Suppress creating of restore point.

-nostop

Don't stop if restore point fails.

-novirusalerts

Suppress virus alerts.

-showdrpnames1

Shows driver pack names on the right.

-showdrpnames2

Shows driver pack names above.

-oldstyle

Puts the match results text underneath the device name rather than to the right.

-hidepatreon

Hides the Patreon button.

Keyboard Actions

Control

Compare the installed driver to the available one (same as expert mode)

Space

Info about alternative drivers (same as opening the sub list of available drivers)

Shift + Control

Same as Space down

Tab

Move forward through control boxes

Shift + Tab

Move backward through control boxes

Cursor Down

Move forward through controls within a control box

Cursor Up

Move backward through controls within a control box

Control + "+"

Increase gui scale

Control + "-"

Decrease gui scale

Control + 0

Reset gui scale

Control + Z

Add a divider line to the log

Control + A

Select all drivers

Control + N

Deselect all drivers

Control + I

Begin driver installation

Control + F5

Rescan devices

Control + F6

Show all possible item bars. Useful for theme development.

F7

Record all desktop windows information to log. Useful for catching rogue installer dialogs.

F8

Cycle through driver pack name display modes.

Scripting

Script mode is still early in development. You should test it thoroughly before using it on mission critical or customer machines. Let me know what bugs you find and what needs to be added. As usual, any loss is your problem, not mine.

Script mode is console only. The main thing to keep in mind is that, being a script, everything happens in a linear fashion, one thing at a time, like a batch file and certain things need to happen before others. A script is a simple text file and can be created with Notepad or your favourite text editor. There's a few example scripts included in the package. If you modify any of these, be sure to rename them so they don't get overwritten by future updates.

Running A Script

To run a script, start SDIO with the `-script:<scriptfile>` command line argument.

For example:

```
SDIO_R580.exe -script:scripts\example-script.txt
```

If the script command is found, all prior arguments on the command line are ignored and the following 9 arguments are fed into the script as %1 through %9 parameters. %0 represents the script file name. These replaceable parameters can be used anywhere within the script. For example, in a goto command.

An example with options:

```
SDIO_R580.exe -script:scripts\example-script.txt option1 option2
```

where:

```
%0 = "scripts\example-script.txt"
```

```
%1 = "option1"
```

```
%2 = "option2"
```

In the script you might have a command like "goto %1" which, in the above example, would expand to "goto option1". A command of "goto %2" would expand to "goto option2".

Config File

The config file is ignored and all command line arguments prior to `-script` are ignored. Therefore, all configuration is done within the script. Make no assumptions except the following defaults.

Defaults:

No log file

No snapshot

Driver directory: "drivers"

Logs directory: "logs"

Indexes directory: "indexes"

Extract directory: "%temp%\SDIO"

Verbose: nothing

Torrent port 50171

If the script doesn't handle your configuration requirements, let me know.

Script Commands

Each line of the script file is one command followed by any arguments, separated by spaces. There is no leading "-" or "/" sign. Any line beginning with "#" or ";" is a comment and is ignored. Any line beginning with ":" is a label used as a target for a "goto" command. Arguments given in triangular brackets, "< >", are required and will give an error if missing. Arguments given in square brackets, "[]", are optional and may be omitted. Defaults may or may not be used for each command.

init [reindex]

Initialises the scripting engine, loads the indexes and drivers, builds any missing indexes and scans the current PC for devices. This should nearly always be done after setting directories and before anything else. It can also be used at any point in the script to reset the engine and allow new driver packs to be indexed locally or a change of path configuration. If the optional "reindex" argument is given, all indexes are rebuilt.

checkupdates

Downloads the latest update torrent and reads it into memory. You must do this before other update commands. If you don't do this or it fails, all subsequent update commands will fail. If you're in an environment where you don't want the torrent client to activate then don't run checkupdates.

get <app | indexes | driverpacks <all | missing | updates | selected> | everything>

Downloads updates. Specify **one** of the given file types:

app

Downloads the latest application, tools, languages, themes and all other files that are not drivers or indexes.

indexes

Downloads the latest online indexes.

driverpacks <all | missing | updates | selected>

Downloads driver packs. Specify one of the given arguments.

- all = missing and updated driver packs

- missing = only missing driver packs
- updates = only updates for driver packs you already have
- selected = only the selected missing and updated driver packs

everything

Downloads the latest of everything: application, indexes and driver packs.

For example:

```
get driverpacks updates
```

select < [missing newer current older better worse] [drpfilters] >

Select the drivers to be installed. The equivalent on the gui is setting the expert filters and then Select All. Specify one or more of the given arguments separated by a space.

For example:

```
select missing newer better
```

To further narrow your selection, you can specify one or more driver pack filters. These are specified by using the middle part (in between the underscores) of the driver pack zip file name. So for example, specify "lan" to include only those drivers found in the "DP_LAN_XXXXX.7z" driver pack. Other examples are: chipset, printer, video, wlan-wifi, wwan-4g.

For example:

```
select missing lan
```

You can specify any combination of regular filters and driver pack filters. Anything that doesn't match one of the six regular filters is assumed to be a driver pack filter. If you specify a non existent regular filter or driver pack filter, nothing will be selected.

install

Install the selected drivers. If drivers are not found locally they will be automatically downloaded if checkupdates previously completed successfully. You don't need to do a 'get' command, just the 'select' and 'install'.

snapshot [filename]

Saves a snapshot to disk. If the optional "filename" argument is specified, the snapshot is saved to that file. If the file name is not given, the snapshot is saved to the logs directory with a time stamp in the file name.

loadsnapshot <filename>

Loads the specified snapshot from disk. This must be placed immediately before the "init" command. The init command will then load the snapshot instead of scanning the PC. In theory you can do this many times in a script.

unloadsnapshot

Returns to "real" mode. This must be placed immediately before the "init" command. The init command will then perform a normal scan of the current PC.

writedevicelist <filename>

Saves the full list of devices and drivers to the given file name.

restorepoint [description]

Create a restore point using the specified description. If no description is given, a default description is used.

logdir <directory>

Sets the log directory to the given directory.

drpdir <directory>

Sets the driver packs directory to the given directory.

indexdir <directory>

Sets the index directory to the given directory.

extractdir <directory>

Sets the temporary directory used for archive extraction. If it's not set, the default is "%temp%\SDIO\"

torrentport <port>

Set the torrent listening port. The default is 50171.

activetorrent <num>

Set the active updates torrent. A value of 1 is the normal SDIO updates, a value of 2 is the driver packs updates.

echo [any text]

Displays the given text to the console.

debug [on|off]

Sets the console/log verbosity to debug. This is the same as LOG_VERBOSE_DEBUG.

logging [on|off]

Enables logging to file.

verbose [verbositeness]

Controls the console/log verbosity. See the *Verbose* chapter earlier for details.

enableinstall [on|off]

Controls whether restore points are actually created and drivers are actually installed. If "on" is specified, restore points are created and drivers are installed. If "off" is specified, all the actions right up to the point of driver installation and/or restore point creation are performed but the actual installation/creation is skipped. This provides a way to test things without trashing your PC.

reboot [ifneeded]

Reboot the machine now. If the optional "ifneeded" argument is specified, reboot will be initiated only if the most recent install command has indicated a reboot is required to complete driver installation.

runlatest [arguments]

Run the latest version of SDIO. Do this after an application update to start using the latest version straight away. The executable architecture is preserved. In other words, if you are currently running the 32 bit version of SDIO then this command will run the latest 32 bit version. If you are currently running the 64 bit version then it will run the latest 64 bit version. You should follow this command in the script with an "end" command to shut down the previous instance of SDIO.

You can include arguments to be added to the SDIO command line. The following example will download the latest application, run the latest version with a script and terminate the current version (the new version will continue to run).

```
get app
runlatest -script:scripts\update-drivers.txt
end
```

pause

Pause script execution until a key is pressed.

cmd <command>

Execute the given command in a command shell.

onerror < end | goto <label> >

Performs the specified action if the previous command resulted in an error.

end

Immediately ends execution of the script.

goto

Transfers script execution to the line following the specified label. The label reference can contain the ":" prefix or not.

goto <label>

Transfers script execution to the line following the specified label. The label reference can contain the ":" prefix or not.

end


End script execution.

Translation Tool

SDIO is currently translated into 38 different languages. With each release, these language translations need to be updated for new and modified strings. You can contribute to any of these translations either by translating new strings or by improving existing translations and forwarding the language file to me at:

translations@snappy-driver-installer.org

The SDIO Translation Tool makes it easy to contribute to language translations. You can run it from the system menu within SDIO or stand alone from the base SDIO directory; it will automatically start with your currently selected language.



Right below the title are tools to change to a different language directory if you have one and a drop down list to select any of the available languages. Your selected language is loaded side by side with the English reference.

At the top right is a colour legend to guide you with which strings require translation:

- Grey Background: This is a comment or section description and cannot be edited
- Orange Background: The translation text is the same as the English reference. This probably means it needs to be translated but it may be that the translation just happens to be the same as the English reference, in which case you can ignore it.
- Red Background: There is no translated text yet. It needs translation.
- Red Text on White Background: There is no English reference text. This means either the value is no longer used or I have neglected to add the reference text. You can't translate this text.

In addition to these, you may also have a suggestion for a better translation of text that has already been translated.

To modify any translation text, simply double click the entry. An edit box will pop up allowing you to edit the text. When you're done, click *Accept* to keep the changes and close the edit box.

After your first edit, the Save and Revert buttons will become enabled allowing you to save or revert your changes to the language file.

The comment lines cannot be edited, blank lines cannot be edited, entries with no English reference text cannot be edited.

